



MATERIALS

Bernat® Softee Baby™ (140 g/5 oz; 331 m/362 yds)

Contrast A Pink (02001) **3 balls**

Contrast B Flannel (30044) **2 balls**

Sizes U.S. G/6 (4 mm) crochet hooks **or size needed to obtain gauge.**

ABBREVIATIONS:

Approx =

Approximate(ly)

Beg = Begin(ning)

Ch(s) = Chain(s)

Dc = Double crochet

Rep = Repeat

RS = Right side

Sc = Single crochet

Sl st = Slip stitch

Sp(s) = Space(s)

St(s) = Stitch(es)

Tog = Together

Yoh = Yarn over hook

WS = Wrong side

 CROCHET | SKILL LEVEL: EASY

MEASUREMENT

Approx 38" [96.5 cm] square.

GAUGE

18 sc and 19 rows = 4" [10 cm].

INSTRUCTIONS

Panel (make 11).

With A, ch 20.

1st row: (RS). 1 sc in 13th ch from hook (turning ch counts as ch 5, 1 dc and ch 4). Ch 3. Miss next ch. 1 sc in next ch. Ch 4. Miss next 4 ch. 1 dc in last ch. Turn.

2nd row: Ch 5 (counts as dc and ch 2). 1 sc in ch-4 sp. Ch 1. 7 dc in ch-3 sp. Ch 1. 1 sc in next ch-4 sp. Ch 2. 1 dc in 3rd ch of ch 5. Turn.

3rd row: Ch 4 (counts as dc and ch 1). Yoh and draw up a loop. Yoh and draw through 2 loops on hook) 4 times in next dc. Yoh and draw through all loops on hook – cluster made. (Ch 3. Miss next dc. Cluster in next dc) 3 times. Ch 1. 1 dc in 3rd ch of ch 5. Turn.

4th row: Ch 5 (counts as dc and ch 2). 1 sc in first ch-3 sp. (Ch 3. 1 sc in next ch-3 sp) twice. Ch 2. 1 dc in 3rd ch of ch 4. Turn.

5th row: Ch 7 (counts as dc and ch 4). 1 sc in next ch-3 sp. Ch 3. 1 sc in next ch-3 sp. Ch 4. 1 dc in 3rd ch of ch 5. Turn.

Rep 2nd to 5th rows until work from beg measures approx 36" [91.5 cm] ending on a 5th row. Fasten off.

Edging: With RS facing, join B with sl st in center ch-1 sp of bottom foundation ch. Ch 3 (counts as dc). 2 dc in same sp. 4 dc in next ch-4 sp. 3 dc in corner. Work 2 dc in each ch-3 sp or around side of each dc up side of Panel to next corner. 3 dc in corner. 4 dc in ch-4 sp. 3 dc in center ch-3 sp. 4 dc in ch-4 sp. 3 dc in corner. Work 2 dc in each ch-3 sp or around side of each dc down side of Panel to next corner. 3 dc in corner. 4 dc in last ch-4 sp. Join with sl st to top of ch 3. Fasten off.

Join Panels: Place WS of Panels tog. With RS facing, join B with sl st in corner dc at bottom edge (working through both thicknesses). Ch 1. 1 sc in same sp. Work 1 sc in each dc up side (working through both thicknesses) to corner dc. Fasten off.