

Free Knitting Pattern

Lion Brand® Wool-Ease® Thick & Quick® Chic Cabled Bag Pattern Number: L40183



Designed by Bobbie Fitzgerald.

Free Knitting Pattern from Lion Brand Yarn

Lion Brand[®] Wool-Ease[®] Thick & Quick Chic Cabled Bag

Pattern Number: L40183

SKILL LEVEL: Easy (Level 2)

SIZE: One Size

About 15 1/2 in. (39.5 cm) wide x 11 in. (28.5 cm) tall, not including Straps

CORRECTIONS: None as of Jul 8, 2014. To check for later updates, click <u>here</u>. **MATERIALS**

- 640-149 <u>Lion Brand</u>
 <u>Wool-Ease Thick & Quick</u>
 <u>Yarn: Charcoal</u>
 3 Balls
- <u>Lion Brand Knitting</u>
 <u>Needles Size 10.5 [6.5 mm]</u>
- <u>Lion Brand Cable Needles</u> (Set of 2)
- <u>Lion Brand Large-Eye</u> Blunt Needles (Set of 6)
- Additional Materials
 Wood dowel, 1/2 in. (13
 mm) diameter and 24 in.
 (61 cm) long
 2 yds. (2 m) of 1 in. (25
 mm) wide grosgrain ribbon
 to match yarn color
 Sewing needle and thread

*<u>Wool-Ease Thick & Quick</u> (Article #640). Solids, Heathers, Twists: 80% Acrylic, 20% Wool

Wheat & Wood: 86% Acrylic; 10% Wool; 4% Rayon

Oatmeal & Barley & Grey Marble: 82% Acrylic; 10% Wool; 8% Rayon

Metallics: 79% Acrylic, 20% Wool, 1% Metallic Poly; package size: Solids,

Heathers, Twists, Tweeds: 6 oz./170g (106 yd/97 m)

Prints, Stripes: 5 oz./140g (87 yd/80 m) Metallics: 5 oz./140g (92 yd/84 m)



GAUGE:

15 sts + 17 rows = about 4 in. (10 cm) in Cable Pattern.

When you match the gauge in a pattern, your project will be the size specified in the pattern and the materials specified in the pattern will be sufficient. The needle or hook size called for in the pattern is based on what the designer used, but it is not unusual for gauge to vary from person to person. If it takes you fewer stitches and rows to make your swatch, try using a smaller size hook or needles; if more stitches and rows, try a larger size hook or needles.

Making a Gauge Swatch


STITCH EXPLANATION:

3/3 LC (3 over 3 left cross) Slip 3 sts to cable needle and hold in front, k3, then k3 from cable needle.

3/3 RC (3 over 3 right cross) Slip 3 sts to cable needle and hold in back, k3, then k3 from cable needle.

NOTES:

- 1. Bag is worked in 4 pieces: Back, Front, and 2 Straps.
- 2. Back and Front are identical. Both are worked in a Cable Pattern with a casing at top edge. The casing is folded and seamed to create a sleeve for the dowels.
- 3. Straps are worked separately, then reinforced with grosgrain ribbon and sewn to Bag.
- 4. Cable Pattern can be worked by following written instructions or by reading the Chart. If working from Chart, read RS rows of chart from right to left and WS rows from left to right.



BACK

Cable Pattern

Cast on 59 sts.

Row 1 (RS): P1, k1, *p2, k9, p2, k1; rep from * 3 more times, p1.

Row 2: K1, *p1, k2, p9, k2; rep from * 3 more times, p1, k1.

Row 3: P1, k1, *p2, 3/3 LC, k3, p2, k1; rep from * 3 more times, p1.

Row 4: Rep Row 2.

Rows 5 and 6: Rep Rows 1 and 2.

Row 7: P1, k1, *p2, k3, 3/3 RC, p2, k1; rep from * 3 more times, p1.

Row 8: Rep Row 2.

Rows 9-40: Rep Rows 1-8.

Rows 41-44: Rep Rows 1-4.

Casing

Row 1 (RS): (K2tog) twice, *k1, (k2tog) twice; rep from * across - 35 sts at the end of this row. Beginning with a WS (purl) row, work in St st (k on RS, p on WS) for 7 rows.

Bind off.

FRONT

Make same as Back.

STRAPS (make 2)

Cast on 4 sts.

Work in Garter st (k every row) until piece measures about 24 in. (61 cm) from beg. Bind off.

FINISHING

With WS of Back and Front tog, sew cast-on edges tog for bottom of Bag. Sew side edges of Back and

Front tog, beg at lower edge and ending about 3 in. (7.5 cm) below first row of casing. Fold Front casing in half toward the inside of Bag and sew edge of casing to inside of Bag. Rep with Back casing. Sew one end of Front Casing closed. Cut dowel to the same length as Front casing and slide into casing. Sew rem end of Front casing closed. Rep to insert dowel into Back casing.

Cut 2 lengths of ribbon, each the same length as Strap. With sewing needle and thread, sew a length of ribbon to one side of each Strap. This is the WS of the Strap.

Pin ends of one Strap to WS of Front, about 1 in. (2.5 cm) in from sides and 1 in. (2.5 cm) below top edge. Sew in place. Rep to attach 2nd Strap to Back.

Weave in ends

| ABBREVIATIONS / REFERENCES Click for explanation and illustration | |
|---|-----------------|
| <pre>beg = begin(s)(ning)</pre> | <u>k = knit</u> |
| k2tog = knit 2 together | p = purl |
| rep = repeat(s)(ing) | RS = right side |
| st(s) = stitch(es) | tog = together |
| WS = wrong side | |

Learn to knit instructions: http://learnToKnit.LionBrand.com

Every effort has been made to have the knitting and crochet instructions accurate and complete. We cannot be responsible for variance of individual knitters and crocheters, human errors, or typographical mistakes.

We want your project to be a success! If you need help with this or any other Lion Brand pattern, e-mail support is available 7 days per week. Just click <u>here</u> to explain your problem and someone will help you!

For thousands of free patterns, visit our website www.LionBrand.com
To order visit our website www.lionbrand.com or call: (800) 258-YARN (9276) any time!

When in New York City, visit the Lion Brand Yarn Studio where we have the largest selection of our yarns anywhere and over 100 classes and events monthly.

34 West 15th Street, NY, NY 10011

Copyright ©1998-2013 Lion Brand Yarn Company, all rights reserved. No pattern or other material may be reproduced -- mechanically, electronically, or by any other means, including photocopying -- without written permission of Lion Brand Yarn Company.