BERNAT® Cable Hat

INTERMEDIATE

SIZE

One size to fit average adult's head.

GAUGE

11 sts and 14 rows = 4" [10 cm] with larger needles in stocking st.

MATERIALS

Bernat® Softee® Chunky™ (3.5 oz/100 g; 108 yds/99 m)	
Woman's Version: Rouge (28531)	**2 balls**
Man's Version: Clay (28041)	**1 ball**

Set of four sizes U.S. 10½ (6.5 mm) and U.S. 11 (8 mm) double-pointed knitting needles **or size needed to obtain gauge.** Cable needle. Stitch marker.

ABBREVIATIONS: www.yarnspirations.com/abbreviations

Beg = Beginning
Cont = Continue(ity)
Cr5B = Slip next 3 stitches onto cable needle and leave at back of work. K2, then (P1. K2) from cable needle
K = Knit
K1tbl = Knit next stitch through back of loop
K2tog = Knit next 2 stitches together
M1 = Make 1 stitch by picking up horizontal loop lying before next stitch and knitting into back of loop

P = Purl
P2tog = Purl next 2 stitches together
Pat = Pattern
Rem = Remaining
Rep = Repeat
Rnd(s) = Round(s)
RS = Right side
St(s) = Stitch(es)
T3B = Slip next stitch onto cable needle and leave at back of work. K2, then P1 from cable needle
T3F = Slip next 2 stitches onto cable needle and leave at front of work. P1, then K2 from cable needle

INSTRUCTIONS

CABLE PANEL (worked over 13 sts). See chart on page 2.
1st row: P4. Cr5B. P4.
2nd row: P4. K2. P1. K2. P4.
3rd row: P3. T3B. P1. T3F. P3.
4th row: P3. K2. P3. K2. P3.
5th row: P2. T3B. P3. T3F. P2.
6th row: P2. K2. P5. K2. P2.
7th row: P2. K2. P5. K2. P2.
8th row: As 6th row.
9th row: P2. T3F. P3. T3B. P2.
10th row: As 4th row.
11th row: P3. T3F. P1. T3B. P3.
12th row: As 2nd row.
These 12 rows form Cable Panel.

With smaller set of needles, cast on 58 sts. Divide sts on 3 needles and join in rnd, placing a marker on first st.
1st rnd: *K1. P1. Rep from * around.
Rep last rnd (K1. P1) ribbing for 3" [7.5 cm].
Next rnd: *Rib 5. M1. Rib 4. M1. Rep from * to last 4 sts. Rib 4. 70 sts.

Change to set of larger needles and proceed in pat as follows:
1st rnd: (K1tbl. Work 1st row Cable Panel across next 13 sts) 5 times.
2nd rnd: (K1tbl. Work 2nd row Cable Panel across next 13 sts) 5 times.
Cable Panel is now in position.
Work a further 10 rnds even in pat, ending on 12th row of Cable Panel.

Shape top: 1st rnd: (K1tbl. P2tog. P2. Cr5B. P2. P2tog) 5 times. 60 sts.
2nd rnd: (K1tbl. P3. K2. P1. K2. P3) 5 times.
3rd rnd: (K1tbl. P2. T3B. P1. T3F. P2) 5 times.
4th rnd: (K1tbl. P2. K2. P3. K2. P2) 5 times.
5th rnd: (K1tbl. P1. T3B. P3tog. T3F. P1) 5 times. 50 sts.
6th rnd: (K1tbl. P1. K2. P3. K2. P1) 5 times.
7th rnd: (K1tbl. P1. K2. P3. K2. P1) 5 times.
8th rnd: As 6th rnd.
9th rnd: (K1tbl. P1. T3F. P1. T3B. P1) 5 times.
10th rnd: (K1tbl. P2tog. K2. P1. K2. P2tog) 5 times. 40 sts.
11th rnd: (K1tbl. P1. K2tog. P1. K2tog. P1) 5 times. 30 sts.
12th rnd: (K1tbl. P1. K3tog. P1) 5 times. 20 sts.
Break yarn leaving a long end. Draw end tightly through rem sts.

Note: One extra ball of yarn will be required for Pompom
Optional Pompom: Wind yarn around 4 fingers 50 times. Tie tightly in the middle and leave a long end for attaching to Hat. Cut loops at both ends and trim to smooth round shape. Sew to top of Hat.



CABLE CHART



Key
□ = Knit on RS rows. Purl on WS rows.
⊟ = Purl on RS rows. Knit on WS rows.
= T3B
= T3F
= Cr5B