

Design S9352 / Man's Pullover



Sizes	S	M	L	XL
Back and Front				
Width at lower edge (in)	19¼	21½	24	26½
Length to beg of armhole (in)	15¾	15¾	15¾	15¾
Armhole width (in)	2½	2½	2½	2½
Armhole depth (in)	9	9½	10	10¼
Neck width (in)	7½	8	8	8¼
Neck depth: Back (in)	1¼	1¼	1¼	1¼
Neck depth: Front (in)	9¼	9¼	9¼	9¼
Shoulder width (in)	3½	4½	5¾	6½
Shoulder depth (in)	¾	¾	¾	¾
Total length (in)	25½	26	26½	26¾
Sleeve				
Width at lower edge (in)	9½	9½	10	10
Width at top edge (in)	18	19	19½	20½
Total length (in)	21½	22½	23¼	24

Sizes: S (M, L, XL)

Instructions are for smallest size with larger sizes in parentheses. If there is only one number, it applies to all sizes.

Materials: Schachenmayr Catania Denim, 600 (650, 700, 750) g in color #00150 navy.
 One pair each sizes US 3 and 4 (3 and 3.5 mm).
 One yarn needle for seaming.

Border Pattern: ★K1, p1; rep from ★ to end.

Texture Pattern:

multiple of 14 sts + 2 selvage sts.

Follow the chart, working RS rows from right to left and WS rows from left to right.

Repeat rows 1 - 10.

Gauge: 23 stitches and 34 rows = 4 x 4"/10 x 10 cm in Texture Pattern using size US 4 (3.5mm) needles.

Full-fashioned Decrease: At beginning of RS rows: k1 (selvage st), work next 7 sts in chart pat, k2 together; at end of RS rows, work to last 10 sts, SKP (slip 1, k1, pass slipped stitch over k1), work next 7 sts in chart pat, k1 (selvage st). Work the selvage stitches in garter stitch (k every row).

INSTRUCTIONS

Back: With size US 3 (3mm) needles, cast on 114 (128, 142, 156) stitches and work in Border Pattern for 2½"/6 cm.

Change to US 4 (3.5) mm needles and work in Texture Pattern, work the 1st (RS) row as follows: K1 (selvage st), work 14-st repeat 8 (9, 10, 11) times, k1 (selvage st).

Cont in pat as established until piece measures 15¾"/40 cm from beginning. For the armhole shaping, bind off 14 stitches at beginning of next 2 rows = 86 (100, 114, 128) stitches.

Work even until piece measures 24¼ (24½, 25, 25½)"/61.5 (62.5, 63.5, 64.5) cm from beginning. For the neck shaping, bind off center 40 (42, 42, 44) sts and working both sides at once, dec 1 st at each neck edge every 2nd row twice.

At the same time, when piece measures 24¾ (25, 25½, 26)"/63 (64, 65, 66) cm from beginning, for the shoulder shaping, bind off from each shoulder edge 7 (9, 12, 14) sts once, and 7 (9, 11, 13) sts twice.

Total length = 25½ (26, 26½, 26¾)"/65 (66, 67, 68cm).

Front: Work same as Back until piece measures 16½ (16¾, 17, 17½)"/41.5 (42.5, 43.5, 44.5) cm from beginning.

For the V-neck shaping, divide the work in half and working both sides at once, work full-fashioned dec at each neck edge every 2nd row 10 (12, 12, 14) times and every 4th row 12 (11, 11, 10) times.

Design S9352 / Man's Pullover

When piece measures 24¾ (25, 25½, 26)" / 63 (64, 65, 66) cm from beginning, work the shoulder shaping same as Back.

Total length = $25\frac{1}{2}$ (26, $26\frac{1}{2}$, $26\frac{3}{4}$)/65 (66, 67, 68) cm.

Sleeves: With size US 3 (3mm) needles, cast on 58 (58, 60, 60) sts and work in Border Pattern for 2½"/6cm.

Change to size US 4 (3.5 mm) needles and work in Texture Pattern, work the 1st (RS) row as follows: K1 (selvage st), k 0 (0, 1, 1), work 14-st repeat 4. times, k 0 (0, 1, 1), k1 (selvage st).

For the sleeve shaping, increase 1 st each side every 4th row 9 (11, 16, 18) times and every

6th row 16 (16, 13, 13) times = 108 (112, 118, 122) sts. Work the increased sts into Texture Pattern.

Work even until piece measures 19¼ (20, 21, 21½)"/49 (51, 53, 55) cm from beginning. Work another 2½"/6 cm. Bind off

Total length = 21½ (22½, 23, 24)"/55 (57, 59, 61) cm.

Finishing: Block pieces to measurements.

Sew shoulder seams. Set in sleeves matching the ★ as shown on the schematic. Sew side and sleeve seams.





Chart for Texture Pattern



Stitch Key

- ☐ = Knit 1 on RS, purl 1 on WS
 ☐ = Purl 1 on RS, knit 1 on WS